


# Connecting your e-mail account to Outlook 2007

Version 1.1

This easy guide will help you set up your Outlook 2007 e-mail program to receive and send e-mail using your new account settings.

1. Open Outlook 2007. Click the **Tools** menu, and then click **Account Settings**.






2. Click your e-mail address so it becomes highlighted.

## Then, click Change...

The Change E-mail Account dialog box will appear.





## 3. Edit the **Incoming mail server** to:


mail.domain.com (where "domain.com" is the last part of your e-mail address)

## Edit the Outgoing mail server (SMTP) to:

**smtp.domain.com** (where "domain.com" is the last part of your e-mail address)

Change the **User Name** to your *full* E-mail Address, including the @ and the domain (such as test@domain.com).

Make sure your Name, E-mail Address, and Password are correct.





 Look for the "Account Type" about halfway down the page: For POP3, continue to step 5.
For IMAP, skip to step 8.

### **POP3 Steps**


5. Click More Settings...

The Internet E-mail Settings dialog box will appear.

Click the **Outgoing Server** tab.

Check the My outgoing server (SMTP) requires authentication box.

Ensure that **Use same settings as my incoming mail server** is selected.






#### 6. Click the **Advanced** tab.

The **Incoming server (POP3)** box should change to "110" automatically.

UNCHECK the **This server requires an encrypted connection (SSL)** box.

Enter "25" in the **Outgoing server (SMTP)** box. \*If your network is blocking port "25" you can use alternate port "587" in this case.

Select **None** from the **Use the following type of encrypted connection** dropdown. \***Please note** that there are a few instances in which the **None** option has failed. In these instances, please select **Auto** from the **Use the following type of encrypted connection** dropdown.






7. Click **OK** to close the More settings dialog box and return to the Change E-mail Account dialog box.

## Click Test Account Settings...

If you receive an error, double-check that all steps were completed correctly and that your Internet connection is active.

When the test is successful, click **Next** to complete the process. Congratulations!





## **IMAP Steps**


8. Click More Settings...

The Internet E-mail Settings dialog box will appear.

Click the **Outgoing Server** tab.

Check the My outgoing server (SMTP) requires authentication box.

Ensure that **Use same settings as my incoming mail server** is selected.






#### 9. Click the Advanced tab.

Select **None** from *both* of the **Use the following type of encrypted connection** dropdowns.

Enter "143" in the Incoming server (IMAP) box.

Enter "25" in the Outgoing server (SMTP) box.





10. Click **OK** to close the Internet E-mail Settings dialog box and return to the Change E-mail Account dialog box.

## Click Test Account Settings...

If you receive an error, double-check that all steps were completed correctly and that your Internet connection is active.

When the test is successful, click **Next** to complete the process. Congratulations!

