

PowerScout 3+ Firmware Update

Version 3.37



Background: The PowerScout 3 Plus has recently received BACnet Testing Laboratory (BTL) certification. As a result, new firmware has been released which enhances the performance of the product. The new firmware also corrects a few other minor issues described below.

Enhancements made in Firmware Version 3.37:

1. BACnet timing has been improved.
2. Individual CT setup registers have been added.
3. Negative and Positive kVA registers have been added in Modbus.
4. The “snap to zero” has been changed from .17% to .04% to support ANSI C12.20-2010 certification.
5. Other minor changes: Objects 10200, 10210, and 10220 have been removed in BACnet. These parameters can be changed through Device Object.

Instruments affected: Serial (PS3P) and Ethernet (PS3E) versions of the PowerScout 3.

Instructions for downloading and installing the firmware update can be found on the DENT website and Appendix G of the PowerScout Manual.

If you have trouble with the download or installation, please contact DENT tech support by phoning 800.388.0770 or 541.388.4774 or emailing Tech Support at techhelp@dentinstruments.com.